

Concept2 PM5 BLE Communication Specification

Overview

This document provides the technical requirements for communicating with Concept2 Performance Monitor 5 (PM5) devices via Bluetooth Low Energy (BLE) in iOS applications.

Base Configuration

UUIDs

- **Base UUID:** `CE06XXXX-43E5-11E4-916C-0800200C9A66`
- Replace `XXXX` with the specific service/characteristic identifier

Device Discovery

- **Device Name:** `PM5 [SerialNumber]` (e.g., "PM5 430000000")
- **Appearance:** `0x0000`

Core BLE Services

1. GAP Service (`0x1800`)

Characteristic	UUID	Type	Permissions	Description
Device Name	<code>0x2A00</code>	String	READ	PM5 device name with serial
Appearance	<code>0x2A01</code>	UInt16	READ	Device appearance (0x0000)
Privacy Flag	<code>0x2A02</code>	UInt8	READ/WRITE	Privacy disabled (0x00)
Reconnect Address	<code>0x2A03</code>	Data	READ/WRITE	00:00:00:00:00:00
Connection Parameters	<code>0x2A04</code>	Data	READ	30ms intervals, 10s timeout

2. Device Information Service (`0x0010`)

Characteristic	UUID	Permissions	Data Type	Description
Model Number	<code>0x0011</code>	READ	String(16)	"PM5"
Serial Number	<code>0x0012</code>	READ	String(9)	Device serial number
Hardware Revision	<code>0x0013</code>	READ	String(3)	Hardware version
Firmware Revision	<code>0x0014</code>	READ	String(20)	Firmware version
Manufacturer	<code>0x0015</code>	READ	String(16)	"Concept2"
Erg Machine Type	<code>0x0016</code>	READ	UInt8	Machine type enum
ATT MTU	<code>0x0017</code>	READ	UInt16	23-512 bytes
LL DLE	<code>0x0018</code>	READ	UInt16	27-251 bytes

3. PM Control Service ((0x0020))

Characteristic	UUID	Permissions	Description
PM Receive	(0x0021)	WRITE	Send CSAFE commands (max 20 bytes)
PM Transmit	(0x0022)	READ	Receive CSAFE responses (max 20 bytes)

4. Rowing Service ((0x0030))

Core Data Characteristics

General Status ((0x0031)) - NOTIFY (19 bytes)

- Bytes 0-2: Elapsed Time (0.01s LSB)
- Bytes 3-5: Distance (0.1m LSB)
- Byte 6: Workout Type (enum)
- Byte 7: Interval Type (enum)
- Byte 8: Workout State (enum)
- Byte 9: Rowing State (enum)
- Byte 10: Stroke State (enum)
- Bytes 11-13: Total Work Distance (1m LSB)

Additional Status 1 ((0x0032)) - NOTIFY (17 bytes)

- Bytes 0-2: Elapsed Time (0.01s LSB)
- Bytes 3-4: Speed (0.001m/s LSB)
- Byte 5: Stroke Rate (strokes/min)
- Byte 6: Heart Rate (bpm, 255=invalid)
- Bytes 7-8: Current Pace (0.01s LSB)
- Bytes 9-10: Average Pace (0.01s LSB)
- Bytes 11-12: Rest Distance
- Bytes 13-15: Rest Time (0.01s LSB)
- Byte 16: Erg Machine Type

Additional Status 2 ((0x0033)) - NOTIFY (20 bytes)

Bytes 0-2: Elapsed Time (0.01s LSB)
Byte 3: Interval Count
Bytes 4-5: Average Power (watts)
Bytes 6-7: Total Calories
Bytes 8-9: Split/Interval Avg Pace (0.01s LSB)
Bytes 10-11: Split/Interval Avg Power (watts)
Bytes 12-13: Split/Interval Avg Calories (cals/hr)
Bytes 14-16: Last Split Time (0.1s LSB)
Bytes 17-19: Last Split Distance (1m LSB)

Sample Rate Control ((0x0034)) - READ/WRITE (1 byte)

0: 1 second intervals
1: 500ms intervals (default)
2: 250ms intervals
3: 100ms intervals

Detailed Data Characteristics

Stroke Data ((0x0035)) - NOTIFY (20 bytes)

Bytes 0-2: Elapsed Time (0.01s LSB)
Bytes 3-5: Distance (0.1m LSB)
Byte 6: Drive Length (0.01m, max 2.55m)
Byte 7: Drive Time (0.01s, max 2.55s)
Bytes 8-9: Recovery Time (0.01s, max 655.35s)
Bytes 10-11: Stroke Distance (0.01m, max 655.35m)
Bytes 12-13: Peak Drive Force (0.1 lbs)
Bytes 14-15: Average Drive Force (0.1 lbs)
Bytes 16-17: Work Per Stroke (0.1 Joules)
Bytes 18-19: Stroke Count

Additional Stroke Data ((0x0036)) - NOTIFY (15 bytes)

Bytes 0-2: Elapsed Time (0.01s LSB)
Bytes 3-4: Stroke Power (watts)
Bytes 5-6: Stroke Calories (cal/hr)
Bytes 7-8: Stroke Count
Bytes 9-11: Projected Work Time (seconds)
Bytes 12-14: Projected Work Distance (meters)

Split/Interval Data ((0x0037)) - NOTIFY (18 bytes)

Bytes 0-2: Elapsed Time (0.01s LSB)
Bytes 3-5: Distance (0.1m LSB)
Bytes 6-8: Split/Interval Time (0.1s LSB)
Bytes 9-11: Split/Interval Distance (1m LSB)
Bytes 12-13: Interval Rest Time (1s LSB)
Bytes 14-15: Interval Rest Distance (1m LSB)
Byte 16: Split/Interval Type
Byte 17: Split/Interval Number

End of Workout Summary (**0x0039**) - NOTIFY (20 bytes)

Bytes 0-1: Log Entry Date
Bytes 2-3: Log Entry Time
Bytes 4-6: Elapsed Time (0.01s LSB)
Bytes 7-9: Distance (0.1m LSB)
Byte 10: Average Stroke Rate
Byte 11: Ending Heart Rate
Byte 12: Average Heart Rate
Byte 13: Min Heart Rate
Byte 14: Max Heart Rate
Byte 15: Drag Factor Average
Byte 16: Recovery Heart Rate
Byte 17: Workout Type
Bytes 18-19: Average Pace (0.1s LSB)

Heart Rate Belt Info (**0x003B**) - NOTIFY (6 bytes)

Byte 0: Manufacturer ID
Byte 1: Device Type
Bytes 2-5: Belt ID (32-bit)

Multiplexed Information (**0x0080**) - NOTIFY (up to 20 bytes)

- First byte is identifier (0x31-0x3F)
- Remaining bytes contain characteristic data
- Only multiplexes when specific characteristic notifications are disabled

Data Type Conversions

Multi-byte Data Construction

Two-byte values (Little Endian)

```
let value = UInt16(data[0]) | (UInt16(data[1]) << 8)
```

Three-byte values (Little Endian)

swift

```
let value = UInt32(data[0]) | (UInt32(data[1]) << 8) | (UInt32(data[2]) << 16)
```

Four-byte values (Little Endian)

swift

```
let value = UInt32(data[0]) | (UInt32(data[1]) << 8) | (UInt32(data[2]) << 16) | (UInt32(data[3]) << 24)
```

Time Conversions

- **Display Time:** 1 second resolution (truncated from 0.01s)
- **Storage Time:** 0.1 second resolution (rounded from 0.01s)
- **BLE Time:** 0.01 second LSB for elapsed time, 0.1s LSB for split times

Distance Conversions

- **Meters:** 1m resolution (no rounding)
- **BLE Distance:** 0.1m LSB for distance, 1m LSB for splits

Pace Conversions

swift

```
// Watts to Pace (seconds per meter)
```

```
func wattsToPace(_ watts: Double) -> Double {  
    return pow(2.8 / watts, 1.0/3.0)  
}
```

```
// Pace to 500m split time
```

```
func paceTo500m(_ pace: Double) -> Double {  
    return pace * 500.0  
}
```

```
// Calories/hr to Pace
```

```
func caloriesToPace(_ calories: Double) -> Double {  
    let watts = (calories - 300.0) / (4.0 * 0.8604)  
    return wattsToPace(watts)  
}
```

CSAFE Protocol (Control Service)

Frame Structure

Standard Frame: [0xF1] [Frame Contents] [Checksum] [0xF2]
Extended Frame: [0xF0] [Dest] [Src] [Frame Contents] [Checksum] [0xF2]

Byte Stuffing

Replace these bytes in frame contents:

- 0xF0 → 0xF3, 0x00
- 0xF1 → 0xF3, 0x01
- 0xF2 → 0xF3, 0x02
- 0xF3 → 0xF3, 0x03

Common Commands

Get Status

Command: [0x80]
Response: [Status Byte]

Set Workout Type

Command: [0x76] [0x02] [0x01] [0x01] [WorkoutType]
WorkoutType: 0=JustRow, 1=JustRow+Splits, 2=FixedDist, etc.

Go to Workout Screen

Command: [0x76] [0x04] [0x13] [0x02] [0x01] [0x01]

Enumerations

Workout Types

swift

```
enum WorkoutType: UInt8 {  
    case justRowNoSplits = 0  
    case justRowSplits = 1  
    case fixedDistNoSplits = 2  
    case fixedDistSplits = 3  
    case fixedTimeNoSplits = 4  
    case fixedTimeSplits = 5  
    case fixedTimeInterval = 6  
    case fixedDistInterval = 7  
    case variableInterval = 8  
    case variableUndefinedRest = 9  
    case fixedCalorieSplits = 10  
    case fixedWattMinuteSplits = 11  
    case fixedCalsInterval = 12  
}
```

Workout States

swift

```
enum WorkoutState: UInt8 {  
    case waitToBegin = 0  
    case workoutRow = 1  
    case countdownPause = 2  
    case intervalRest = 3  
    case intervalWorkTime = 4  
    case intervalWorkDistance = 5  
    case workoutEnd = 10  
    case terminate = 11  
    case workoutLogged = 12  
    case rearm = 13  
}
```

Rowing States

swift

```
enum RowingState: UInt8 {  
    case inactive = 0  
    case active = 1  
}
```

Stroke States

swift

```
enum StrokeState: UInt8 {
    case waitingForWheelToReachMinSpeed = 0
    case waitingForWheelToAccelerate = 1
    case driving = 2
    case dwellingAfterDrive = 3
    case recovery = 4
}
```

iOS Implementation Notes

BLE Connection

```
swift

// Service UUIDs
let deviceInfoServiceUUID = CBUUID(string: "CE060010-43E5-11E4-916C-0800200C9A66")
let controlServiceUUID = CBUUID(string: "CE060020-43E5-11E4-916C-0800200C9A66")
let rowingServiceUUID = CBUUID(string: "CE060030-43E5-11E4-916C-0800200C9A66")

// Key characteristics
let generalStatusUUID = CBUUID(string: "CE060031-43E5-11E4-916C-0800200C9A66")
let strokeDataUUID = CBUUID(string: "CE060035-43E5-11E4-916C-0800200C9A66")
let controlReceiveUUID = CBUUID(string: "CE060021-43E5-11E4-916C-0800200C9A66")
```

Data Parsing Example

```
swift

func parseGeneralStatus(_ data: Data) -> GeneralStatus {
    let elapsedTime = UInt32(data[0]) | (UInt32(data[1]) << 8) | (UInt32(data[2]) << 16)
    let distance = UInt32(data[3]) | (UInt32(data[4]) << 8) | (UInt32(data[5]) << 16)
    let workoutType = WorkoutType(rawValue: data[6]) ?? .justRowNoSplits

    return GeneralStatus(
        elapsedTime: Double(elapsedTime) / 100.0, // Convert from 0.01s
        distance: Double(distance) / 10.0,        // Convert from 0.1m
        workoutType: workoutType,
        // ... parse remaining fields
    )
}
```

Important Considerations

1. **Connection Parameters:** Use 30ms connection intervals for optimal performance
2. **MTU Size:** Negotiate larger MTU (up to 512 bytes) for better throughput

3. **Notification Management:** Enable only needed characteristics to reduce bandwidth
4. **Sample Rate:** Set appropriate sample rate (default 500ms) based on application needs
5. **Data Validation:** Always validate data ranges and handle invalid values (e.g., HR = 255)
6. **Error Handling:** Implement robust error handling for BLE disconnections and data parsing

Battery Considerations

- PM5 uses 2xD cell batteries
- Monitor battery level through status notifications
- Implement power-efficient connection parameters
- Handle low battery disconnections gracefully

Testing Recommendations

- Test with various workout types and states
- Verify data parsing with extreme values
- Test connection stability during extended sessions
- Validate pace/power calculations against PM5 display